

11.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers.

```
if ($t0 == 0) {
    $t1 = 5;
}

    bne $t0, $zero, after_if
    li $t1, 5
after_if:
```

12.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers.

```
if ($t0 < 5) {
    $t1 = 0;
} else {
    $t1 = 1;
}

    slti $t3, $t0, 5
    beq $t3, $zero, else_branch
    li $t1, 0
    j after_if
else_branch:
    li $t1, 1
after_if:
```

13.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers.

```
if ($t0 == 0 || $t1 == 1) {
    $t2 = 5;
} else {
    $t2 = 6;
}
```

```
beq $t0, $zero, true_branch
li $t3, 1
beq $t1, $t3, true_branch
li $t2, 6
j after_if
true_branch:
li $t2, 5
after_if:
```

14.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers.

```
if ($t0 >= 0 && $t0 < $t1) {
    $t2 = 9;
} else {
    $t2 = 0;
}
```

```
# !($t0 >= 0 && $t0 < $t1) ==> $t0 < 0 || $t0 >= $t1
slt $t3, $t0, $zero # $t0 < 0?
bne $t3, $zero, else_branch # if yes, jump to else
# $t0 >= $t1 ==> !($t0 < $t1)
slt $t3, $t0, $t1 # $t0 < $t1?
beq $t3, $zero, else_branch # if not, jump to else
li $t2, 9
j after_if
else_branch:
li $t2, 0
after_if:
```

15.) Write a MIPS program that will read integers from the user until 0 is input. Once 0 is input, the program should print the sum of all the numbers read in. As a hint, you should track a running sum, instead of trying to store all the numbers the user read in. If the user immediately inputs a 0, then the running sum should be 0.

```
.text
main:
    # $t0: running sum
    # $t1: input number
    li $t0, 0

    # $t1 = readNum()
    # while ($t1 != 0) {
    #     $t0 = $t0 + $t1
    #     $t1 = readNum()
    # }
    # print($t0)

    li $v0, 5
    syscall
    move $t1, $v0
loop_begin:
    beq $t1, $zero, loop_end
    add $t0, $t0, $t1
    li $v0, 5
    syscall
    move $t1, $v0
    j loop_begin
loop_end:
    move $a0, $t0
    li $v0, 1
    syscall

    li $v0, 10
    syscall
```

16.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers.

```
$t0 = 10
$t1 = 1
$t2 = 0
while ($t1 <= $t0) {
    $t2 = $t2 + $t1;
    $t1++;
}
```

```
.text
main:
    li $t0, 10
    li $t1, 1
    li $t2, 0
loop_begin:
    # $t1 <= $t0 ==> !($t1 > $t0) ==> !($t0 < $t1)
    slt $t3, $t0, $t1
    # $t3 == 0 if $t0 < $t1, meaning !($t1 > $t0), meaning $t1 <=
    $t0
    # $t3 == 1 if !($t1 <= $t0)
    bne $t3, $zero, loop_end
    add $t2, $t2, $t1
    addi $t1, $t1, 1
    j loop_begin
loop_end:
    li $v0, 10
    syscall
```

17.) Write a MIPS program that will read in an integer, and will print one of two things:

- Bit 2 is set
- Bit 2 is not set

...depending on whether or not bit 2 of the input number is set. To be clear, bit 0 refers to the rightmost bit in the number.

```
        .data
is_set_string:
        .asciiz "Bit 2 is set\n"
is_not_set_string:
        .asciiz "Bit 2 is not set\n"

        .text
main:
        # $t0: the number

        # read in the integer
        li $v0, 5
        syscall
        move $t0, $v0

        # mask out all other bits
        andi $t0, $t0, 0x4

        beq $t0, $zero, is_not_set
        la $a0, is_set_string
        j after_if
is_not_set:
        la $a0, is_not_set_string
after_if:
        # print the string
        li $v0, 4
        syscall

        # exit the program
        li $v0, 10
        syscall
```

18.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers.

```
int s0 = 82;
int s1 = s0 << 2;
int s2 = s1 * 20;
int s3 = s2 + 7;
int s4 = s3 - 24;
int s5 = s4 / 3;
```

```
main:
    li $s0, 82          # int s0 = 82;

    sll $s1, $s0, 2     # int s1 = s0 << 2;

    li $t0, 20          # int s2 = s1 * 20 (part 1 of 3)
    mult $s1, $t0       # (part 2 of 3)
    mflo $s2            # (part 3 of 3)

    addi $s3, $s2, 7    # int s3 = s2 + 7

    li $t1, 24          # int s4 = s3 - 24 (part 1 of 2)
    sub $s4, $s3, $t1   # (part 2 of 2)

    li $t2, 3           # int s5 = s4 / 3 (part 1 of 3)
    div $s4, $t2        # (part 2 of 3)
    mflo $s5            # (part 3 of 3)
```

19.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers. The portions in <<>> will require you to use QtSpim functionality. You do not need to exit the program properly.

```
int s0 = <<read integer from the user>>;
int s1 = 2;
if (s0 < 7) {
    s1 = 3;
}
<<print integer s1>>
```

```
main:
    # read integer from user
    li $v0, 5
    syscall

    # save integer from user
    move $s0, $v0

    # store 2 in s1
    li $s1, 2

    # check if s0 < 7
    li $t0, 7
    slt $t1, $s0, $t0

    # if it's NOT less than 7, skip the body of the if
    beq $t1, $zero, printmsg

    # we didn't branch, meaning s0 < 7
    li $s1, 3

printmsg:
    # print s1
    li $v0, 1
    move $a0, $s1
    syscall
```

20.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers. The portions in <<>> will require you to use QtSpim functionality. You do not need to exit the program properly.

```
int s0 = <<read integer from the user>>;
int s1 = 2;
if (s0 < 7) {
    s1 = 3;
} else {
    s1 = s0 + s0;
}
<<print integer s1>>
```

```
main:
    # read in the integer from the user, and initialize s1
    li $v0, 5
    syscall
    move $s0, $v0
    li $s1, 2

    # check if $s0 < 7
    li $t0, 7
    slt $t1, $s0, $t0

    # jump to the else branch if this isn't true
    beq $t1, $zero, else_branch

    # fall through to the true branch
    li $s1, 3
    j print

else_branch:
    add $s1, $s0, $s0
    # fall through to the print

print:
    li $v0, 1
    move $a0, $s0
    syscall
```


21.) Convert the following C-like code into MIPS assembly. The names of the variables reflect which registers must be used for the MIPS assembly. Do not assume any initial values for the registers. You may use additional registers. The portions in <<>> will require you to use QtSpim functionality. You do not need to exit the program properly.

```
int s0;
int s1 = 1;
for (s0 = 0; s0 < 10; s0++) {
    s1 = s1 * s0;
}
```

```
main:
    # initialize variables
    li $s0, 0
    li $s1, 2
loop:
    # check loop condition
    li $t0, 10
    slt $t1, $s0, $t0          # s0 < 10?
    beq $t1, $zero, loop_exit # if not, jump to loop_exit

    # do body of the loop
    mult $s1, $s0
    mflo $s1

    # increment counter
    addi $s0, $s0, 1
    j loop

loop_exit:
    # this is past the loop
```